

Role Management

Created by Dennis Underwood, last modified by Mark Weideman on Feb 12, 2025

- [Creating a Role](#)
- [Assigning Roles to Users](#)
- [Deleting a Role from a Group](#)
- [Editing a Role's Permissions](#)

By default, there are three built-in roles:

- Guest has no permissions.
- Read Only grants read only permissions to tailored behaviors, silent responses, and partner deals.
- Admin gives full read and write access to all portions of the web application.

Creating a Role

Custom roles may be created with granular control.

Find the Create New Role button under the Administration → Roles section of the web application.

85032971.png?width=680

After clicking on the Create Role button, enter the Role Name, select the Group to add the Role to, and select the permissions associated with the Role.

85557251.png?width=680

Assigning Roles to Users

On the Roles Page, each row on the grid represents a user inside a group and their assigned roles inside that group. To assign a role to a user inside a group, or remove a role from a user, click the toggle inside the column for the desired role.

85164051.png?width=680

When a role is assigned to a user, the toggle will be flipped to the right and will look like:

85196841.png?width=680

Deleting a Role from a Group

On the Roles Page, each row on the grid represents a user inside a group and their assigned roles inside that group. To delete a role inside a group, find the desired role (represented by a column) for the group you are deleting it from, and click the trash icon inside the cell. Note that default roles cannot be deleted.

85393426.png?width=680

Editing a Role's Permissions

On the Roles Page, each row on the grid represents a user inside a group and their assigned roles inside that group. To edit a role's permissions for a group, find the desired role (represented by a column) for the group you are editing it for, and click the edit icon inside the cell. This will popup the Edit Role modal and show the current permissions associated with the role, which you are able to change. Note that default roles cannot be edited.

85426206.png?width=680

Edit Role: User

Change Role Name

User

Group

Select

Test Group

Permissions

☐ Agent Manager

☐ Change Agent Group

☐ Uninstall Agent

☐ Change Agent Auto-Upgrade

☐ Change Agent Name

☐ Release Agent License

☐ Change Collect Agent Telemetry

☐ Change Agent Grid Visibility

☐ Group Manager

☐ Add User To Group

☐ Remove User From Group

☐ Change User Role

☐ Change Group Name

☐ Create Group

☐ Edit Session Duration

☐ View Session Duration

☐ Edit Group Use WHCP Drivers Only

☐ Upload SSL Certificate

☐ Remove SSL Certificate

☐ Edit Group SSL Pinning Mode

☐ Incident Manager

☐ Ignore Incident

☐ Safe Kill Process

☐ Unsafe Kill Process

☐ Isolate Process

☐ Dismiss Process

☐ Suspend Process

☐ Edit Whitelist Name

☐ Remove Whitelist Name

☐ Silence Incident

☐ Appliance Manager

☐ Create Appliance

☐ View Appliance

☐ Create Appliance Job

☐ Cancel Appliance Job

☐ View Appliance Job

☐ Response Automation Manager

☐ Create Schedule

☐ Edit Schedule

☐ Delete Schedule

☐ Notification Manager

☐ Create Notification

☐ Edit Notification

☐ Delete Notification

☐ Purchase Manager

☐ Purchase Licenses

☐ Edit Partner Deal Name

☐ Remove Partner Deal Name

Cancel

Update

Revision #2

Created 2026-05-18 20:29:26 UTC by Dennis Underwood

Updated 2026-05-18 20:40:47 UTC by Dennis Underwood